



# AMSIMOD

## USER'S GUIDE

**Guy R. Larocque, Charles-David Lachance, Mikael Jonathan Luce,  
Patrick Munro, Pier-Olivier Pichette Côté, Mildred Deldago,  
Pascale-Nicole Lapointe and Jonathan Hamel**



Laurentian Forestry Centre  
Information Report LAU-X-139E

© Her Majesty the Queen in Right of Canada 2019  
Catalogue Number Fo113-3/139E-PDF  
ISBN 978-0-660-33176-8  
ISSN 0835-1570

This publication is available in PDF at no charge from the Canadian Forest Service Bookstore at:  
<http://cfs.nrcan.gc.ca/publications>

TTY: 613-996-4397 (teletype for the hearing impaired).

Cette publication est également offerte en français sous le titre **AMSIMOD, Guide de l'utilisateur** (numéro de catalogue Fo113-3/139F-PDF).

- Information contained in this publication or product may be reproduced, in part or in whole, and by any means, for personal or public non-commercial purposes, without charge or further permission, unless otherwise specified.
- You are asked to:
  - exercise due diligence in ensuring the accuracy of the materials reproduced;
  - indicate the complete title of the materials reproduced, and the name of the author organization; and
  - indicate that the reproduction is a copy of an official work that is published by the Government of Canada and that the reproduction has not been produced in affiliation with, or with the endorsement of, the Government of Canada.
- Commercial reproduction and distribution is prohibited except with written permission from the Government of Canada's copyright administrator, Public Works and Government Services Canada (PWGSC). For more information contact PWGSC at 613-996-6886 or at [droitdauteur.copyright@tpsgc-pwgsc.gc.ca](mailto:droitdauteur.copyright@tpsgc-pwgsc.gc.ca).

## TABLE OF CONTENT

<b>1- Introduction</b> .....	7
<b>2- Installation of AMSIMOD</b> .....	7
<b>3- Structure of AMSIMOD</b> .....	7
3.1- File menu .....	7
3.2- Edit menu .....	11
3.3- Simulation menu.....	11
3.4- View menu .....	11
3.5- Graph menu .....	12
3.5.1- Line graph submenu .....	12
3.5.1.1- Simple graphs for visualizing simulation results .....	12
3.5.1.2- Stratified graphs for visualizing simulation results.....	14
3.5.2- Histograms.....	18
3.6- Visual Add-ons menu .....	18
3.7- QGIS menu .....	20
3.7.1- Installating and running Quantum GIS .....	20
3.7.2- Plugins .....	21
3.8- Extensions menus .....	24
3.9- Windows menu.....	25

## LIST OF APPENDICES

<b>Appendix 1:</b> Example of the information provided to run a model within a project. There is one input file and five output files .....	26
<b>Appendix 2:</b> Example of C/C++ code to read input and output file names that are included in a project simulation .....	27
<b>Appendix 3:</b> Example of the format of a data file to draw histograms .....	29
<b>Appendix 4:</b> Examples of two plot position files, generated by the application “Create_Plot_Position_Files.exe” (Appendix 5), that contain information and spatial data for individual sample plots.....	30

<b>Appendix 5:</b> Introduction to the application “Create_Plot_Position_Files.exe” .....	31
<b>Appendix 6:</b> Example of pie charts produced by the TimeViwer plugin on a digital map in Quantum GIS .....	33

## LIST OF FIGURES

<b>Figure 1:</b> Illustration of the main window and menu bar of AMSIMOD .....	8
<b>Figure 2:</b> Form that opens when the command “New workspace” is selected in the file menu to enter the name of a workspace and select its location on a hard disk.....	8
<b>Figure 3:</b> Input window to enter the name of a new project .....	9
<b>Figure 4:</b> Input window to add or edit a model in a project.....	10
<b>Figure 5:</b> Input form to enter the name of a simulation, the executable file of a model or application and the names of the initialization, intervention and output files .....	11
<b>Figure 6:</b> Example of a form that includes the list of the state variables in an output file that can be displayed on a simple graph .....	13
<b>Figure 7:</b> Selection of different output files to display average simulation results.....	13
<b>Figure 8:</b> Example of a simple graph showing average results by combining several output files .....	14
<b>Figure 9:</b> Selection of the number of error bars associated with the time cycles to display on a graph that contains average simulation results.....	14
<b>Figure 10:</b> Selection of two stratification variables, 1 category variable and 1 output variable for a stratified graph.....	16
<b>Figure 11:</b> Selection of specific simulation results associated with a category variable to display on a stratified graph.....	16
<b>Figure 12:</b> Form that opens after the selection of output files from different simulation results is completed.....	17

<b>Figure 13:</b> Example of a stratified graph showing average results with error bars .....	17
<b>Figure 14:</b> Input window to select the stratification and category variables to produce a distribution histogram .....	19
<b>Figure 15:</b> Following the identification of stratification and category variables, this form allows the selection of a particular source of results, such as a sample plot, at different time cycles.....	19
<b>Figure 16:</b> Selection of input files to display average values on histograms .....	20
<b>Figure 17:</b> Form that opens when the command “Setup” is selected in the QGIS menu to enter the location of the executable file of Quantum GIS and the location and name of a digital map .....	21
<b>Figure 18:</b> Form that requests the name of a file, such as QGIS_Output.txt, containing the names of the files that include the information and names of plot position files, such as those in Table 3.....	22
<b>Figure 19:</b> Illustration of the TimeViewer window that becomes visible in Quantum GIS when it is activated in the Plugins menu.....	23
<b>Figure 20:</b> Illustration of the input window in TimeViewer to set the number of categories on pie charts and select a category variable and a quantitative variable to display on pie charts .....	24
<b>Figure 21:</b> Examples of available applications in the menu “Extensions” .....	25

## LIST OF TABLES

<b>Table 1:</b> Example of simulation results that can be displayed on a “Simple graph” .....	12
<b>Table 2:</b> Example of a simulation result file with different sources of results. Plot_ID\$ and Plot_num\$ are stratification variables and Species& is a category variable .....	15

**Table 3:** Example of the content of an input file provided to the plugin “Position plots” that contains the labels for the identification of sample plots (e.g., Edouard\_CO 65), type of coordinates used (e.g., 1) and plot position file names for sample plots to position on a digital map.....22

**Table 4:** Example of the format of a result file to display circular charts .....24

## 1- Introduction

AMSIMOD (Application for the Management of Simulation MODEls) is a modelling software platform that facilitates the development and management of different types of forest models. Many forest models have been developed, but few of them come with utilities that facilitate the management of simulation runs and the visualization of simulation results. Several software platforms have been developed to manage models. They can be classified in three categories: (1) software frameworks, (2) modelling tools and (3) simulators. However, these applications generally do not include utilities to integrate a variety of models or display simulation results on different scales or formats.

End-users of AMSIMOD can define projects that contain models, input and output files and, if necessary, intervention files to simulate the effects of disturbance scenarios. The objective of this user guide is to describe the different functionalities of AMSIMOD.

## 2- Installation of AMSIMOD

AMSIMOD can be downloaded from <https://apps-scf-cfs.mcan.gc.ca/calc/en/ecosysmodel>. It can be installed anywhere on a hard drive. For instance, it can be installed on “C:\Program Files (x86)” using the installer file provided. However, it is preferable to install it on the first level of a hard drive or on the partition C:\, particularly for end-users who do not have an administrator account on their computer.

## 3- Structure of AMSIMOD

The main window of AMSIMOD with first-level menus is illustrated on Figure 1. The active workspace and project (“project loaded”) are indicated. A workspace is the name and location of a folder (directory) that contains projects, models, input and output files or any other type of information or data that may be used in simulations. A project contains the information needed, including models, input and output files, to run simulations (see below).

### 3.1- File menu


The first two commands in the file menu can be used to create a new workspace or change the active workspace, respectively (Figure 2). A workspace can be located anywhere on a hard disk. For instance, a workspace called “Sim\_Forest” may be located on the C drive within a folder “Projects”. Thus, the workspace is “C:\Projects\Sim\_Forest” and becomes the active workspace. The command “Change Workspace” allows end-users to change the active workspace. As it is

possible to define several workspaces within hard drives, this submenu facilitates workspace browsing.

*Note: It is preferable not to insert spaces in workspace names. However, the character underline (“\_”) is acceptable as separator of workspace names, such as, “Sim\_Forests”.*




**Figure 1:** Illustration of the main window and menu bar of AMSIMOD.



**Figure 2:** Form that opens when the command “New workspace” is selected in the file menu to enter the name of a workspace and select its location on a hard disk.




The third command, “New Project” is used to define a new project in a workspace. When selected, a form opens to request a project name (Figure 3). When the “Ok” button is selected, the extension “.pro” is added to the name of a project and a folder (directory) containing the name of the project followed by “\_results” is created within the current workspace. All the output files created by models following their execution will be saved in this folder. For instance, if the name of a project is “Forest\_Sim”, the folder “Forest\_Sim\_results” will be created and the output files of simulation runs will be saved in this folder



**Figure 3:** Input window to enter the name of a new project.

If the name of a project contains distinct words that should be separated, the “\_” (underline) character must be used instead of a blank character (space) to separate them (e.g., Project\_Forest). Once the name of a project is entered, a form opens to add one or several models in a project (Figure 4). By clicking on “Add a model”, the form “Simulation Setup” opens to enter the simulation name, the executable file (ending with .exe) of a model (e.g., Growth\_Forest.exe) and initialisation (input), intervention and output files (Figure 5). The executable, initialisation and intervention files must be located within the active workspace. Only one executable file of a model is allowed within a simulation, but a project may contain several simulations using different models. A simulation may contain as many input, intervention and output files as necessary to run a simulation. For every file of a simulation, it is possible to include comments by clicking on the button “Comments”. This utility is very useful when a project contains several models and input, intervention and output files. An example of the information provided to run a model within a project is included in Appendix 1. For AMSIMOD, the code of a model can be developed in any programming language, as long as a stand-alone executable file (.exe or .bat) is included in the definition of a project. Input, intervention and output files provided in a simulation must be sequentially associated with the instructions in the code of a model that requests input, intervention and output files. Appendix 2 contains an example that reads input and output file names in the C/C++ language.



**Figure 4:** Input window to add or edit a model in a project.

The fourth command, “Open a project”, is used to open an existing project in the active workspace. When a project is selected, the project form opens and all the simulations of a project are listed. It is possible to add or edit simulations of a project.


The fifth command, “Open graphic file”, is used to import simulation results that were saved in a graphic format.

The sixth command “Language” is used to choose the language of AMSIMOD, either English or French. When selected, all the menus, commands and the texts in the main window and forms will appear in the language selected by the user.

The last command, “Exit”, ends the execution of AMSIMOD.

### 3.2- Edit menu

The “Edit” menu is used to modify an existing project. The project window opens and lists all the simulations that are included in a project.



**Figure 5:** Input window to enter the name of a simulation, the executable file of a model or application and the initialization, intervention and output files.

### 3.3- Simulation menu

When “Run” is selected, all the models of a project are executed sequentially. It is possible to stop the execution of the models within a project by selecting “Stop simulation”.

### 3.4- View menu

The command “Project comments” displays the comments that were provided in the system when a new project was defined or an existing project modified. This functionality may be very useful as a checklist, particularly when a project contains several models and input, intervention and output files. The command “Available projects” lists all the projects that exist in the workspace identified just below the menu bar.

### 3.5- Graphs menu

Modellers or end users of models generally prefer to display simulation results on graphs. AMSIMOD includes utilities in the “Graphs” menu to draw line graphs or histograms. Once a graph type is selected, a data file type “.txt” must be entered. The files used to draw graphs usually consist of files that contain simulation results that are normally found in the folders of simulation results (ending with “\_results”). The first line in simulation result files must contain the names of the variables. The variable name for time (e.g., year, day or hour) must be placed in the first position (column). A maximum of 20 characters may be used for variable names. Letters, digits or the underline (“\_”) character are allowed in variable names. The ampersand (&) and dollar (\$) signs are used at the end of a variable name to identify stratification or category variables (see below).

#### 3.5.1- Line graph Submenu


The submenu “line graph” allows the visualization of simulation results on simple or stratified graphs. For both simple and stratified graphs, it is possible to display the results of a particular simulation by selecting “Single results” or the average of several simulation results by selecting “Average results”.

##### 3.5.1.1- Simple graphs for visualizing simulation results

The “Simple graph” second-level submenu may be used to display simulation results from a single source of values, such as the results of a simulation containing results for a single sample plot (e.g., Table 1), by selecting the command “Single results”. Once a file is selected, a form lists the variables that are available for display on a simple graph (Figure 6). A maximum of five variables can be selected for a simple graph, but there is no limit on the number of graphs that can be created.


**Table 1:** Example of simulation results that can be displayed on a “Simple graph”

Year	Resp_Litter	Root_Resp	FH_Resp	Min_Resp	FH_Min
1	1356	908	1119	1766	2885
2	1368	947	1058	1614	2672
3	1380	965	982	1463	2446
4	1391	973	914	1372	2287
5	1401	977	859	1319	2179
Etc.					




**Figure 6:** Example of a form that includes the list of the state variables in an output file that can be displayed on a simple graph.


The results of several simulation result files may be combined to display average values by selecting the command “Average results” in the “Simple graph” submenu. The files must be selected from the list of files within a result directory (Figure 7). An example of a graph that displays average results is shown on Figure 8. Error bars, which consist of standard deviations, can be added by selecting “Manage error bars” in the “Action” menu of the graph (Figure 9). The number of error bars to display can be selected in the Combo box on the right.



**Figure 7:** Selection of different output files to display average simulation results.



**Figure 8:** Example of a simple graph showing average results by combining several output files.



**Figure 9:** Selection of the number of error bars associated with the time cycles to display on a graph that contains average simulation results.


### 3.5.1.2- Stratified graphs for visualizing simulation results

A stratified graph facilitates the visualization of simulation results from different sources of results, such as results for different sample plots. Table 2 is an example of an output file with different sources of results. “Plot\_ID\$” and “Plot\_num\$” are stratification variables that are used to differentiate the sources of simulation results. Stratification variables end with the character “\$”. In the example of Table 2, “Plot\_ID\$” and “Plot\_num\$” indicate that the simulation results were output for different sample plots identified by a forest type (e.g., Edouard\_CO ou Edouard\_VI\_O) and a sample plot number. A maximum of three stratification variables can be used to draw a


stratified graph. “Species&” in Table 2 is used to identify the instances of a state variable that will be displayed on a graph. For example, “Species&” in Table 2 indicates that basal area will be displayed on a graph for different species and simulation periods. When “Single results” is selected in the “Stratified graph” submenu, a result file must first be selected. Following the selection of a result file, a form opens to select a maximum of 3 stratification variables (listed under the heading “Available”) by clicking on “>”, 1 category variable (selected from a Combo box) and 1 output variable (Figure 10). Once this information is provided, a second form opens to select specific simulation results associated with a category variable to display (Figure 11). For the example of Figure 11, the end user can select from the Combo boxes the simulation results of a particular sample plot identified by its forest type (Plot\_ID) and plot number (Plot\_num). A maximum of 5 attributes of a category variable (Species in the example of Figure 11) can be displayed on a graph, but several stratified graphs can be created during an AMSIMOD session.

**Tableau 2:** Example of a simulation result file with different sources of results. Plot\_ID\$ and Plot\_num\$ are stratification variables and Species& is a category variable.

Year	Plot_ID\$	Plot_num\$	Species&	Basal_area (m**2/ha)
0	Edouard_CO	65	Yellow_birch	2.15
0	Edouard_CO	65	White_birch	1.80
0	Edouard_CO	65	Red_spruce	22.12
0	Edouard_CO	65	Red_maple	0.31
0	Edouard_CO	65	Balsam_fir	10.76
0	Edouard_CO	65	Northern_whitecedar	0.72
25	Edouard_CO	65	Yellow_birch	0.11
25	Edouard_CO	65	White_birch	0.24
25	Edouard_CO	65	Red_spruce	28.80
25	Edouard_CO	65	Balsam_fir	3.11
25	Edouard_CO	65	Northern_whitecedar	0.17
0	Edouard_VI_O	67	Yellow_birch	6.78
0	Edouard_VI_O	67	White_birch	4.74
0	Edouard_VI_O	67	Red_spruce	2.99
0	Edouard_VI_O	67	Red_maple	0.53
0	Edouard_VI_O	67	Sugar_maple	0.65
0	Edouard_VI_O	67	Balsam_fir	1.41
0	Edouard_VI_O	67	Northern_whitecedar	0.49
20	Edouard_VI_O	67	Yellow_birch	5.41
20	Edouard_VI_O	67	White_birch	4.71
20	Edouard_VI_O	67	Red_spruce	4.37
20	Edouard_VI_O	67	Mountain_maple	0.90
20	Edouard_VI_O	67	Striped_maple	0.02
20	Edouard_VI_O	67	Sugar_maple	0.24
20	Edouard_VI_O	67	Balsam_fir	3.53
20	Edouard_VI_O	67	Northern_whitecedar	0.97



**Figure 10:** Selection of two stratification variables, 1 category variable and 1 output variable for a stratified graph.



**Figure 11:** Selection of specific simulation results associated with a category variable to display on a stratified graph.


A stratified graph can also be created to display the averages of several simulation results by selecting “Average results” in the “Stratified graph” second-level submenu. The result files are selected from the list of files within a result directory (see Figure 7). Once the selection of result files is completed, a form opens to select the stratification and category variables (Figure 12). In the example of Figure 12, the two stratification variables are “Plot\_ID” and “Plot\_num”. It is possible to select three forest types (Edouard\_CO, Edouard\_VI\_O or Edouard\_O\_CO) and sample plot numbers associated with each forest type. As the category variable is “Species” in the example



of Figure 12, the list of species that can be displayed are then listed to produce a graph showing average simulation results along with error bars (standard deviations) (Figure 13).

The dialog box titled "Select state variables" contains several sections. On the left, under "Stratification variables", there are two lists: "Available" (containing Plot\_ID and Plot\_num) and "Selected" (also containing Plot\_ID and Plot\_num). Between these lists are ">" and "Remove" buttons. To the right, there is a "Category variable" dropdown menu set to "Species", and an "Output variable(s)" list containing "Basal\_area\_m^2/t" with a checked checkbox. Further right is a "Selected Files" list containing "BA\_Out\_test.txt" and "BA\_Out\_test\_2.txt". At the bottom left is a "Graphic title" text field. At the bottom right are "Back" and "Ok" buttons.

**Figure 12:** Form that opens after the selection of output files from different simulation results is completed.



**Figure 13:** Example of a stratified graph showing average results with error bars.

### 3.5.2- Histograms

The “Histogram” submenu is used to draw histograms to visualize simulation results of frequency distributions. The number of trees by diameter at breast height (dbh) classes is a good example of histograms commonly used to visualize stand density values by dbh classes. An example of the format of a result file to draw a histogram is found in Appendix 3. The first line contains the labels for the time cycle, which must be in the first position, stratification variables (Plot\_ID\$ and Plot\_num\$ in the example of appendix 3), a category variable (Species& in the example of Appendix 3), the label for the X-axis, minimum and maximum values for each class of the variable in the X-axis and the label for the Y-axis. The label for the X-axis ends with the “@” (at) symbol. The minimum and maximum values for each class are separated using the hyphen mark. For AMSIMOD, the minimum class value is interpreted as data in this class that are greater or equal ( $\geq$ ) to this value, while the maximum value is interpreted as smaller ( $<$ ) than this value. The last class is identified by a single value followed by the hyphen mark and is interpreted as greater or equal. There is no limit on the number of frequency classes, but it is preferable not to have more than 10 classes.

There are two options to draw histograms. The command “Distribution histogram” is used to draw histograms for a single data source, such as a sample plot. Once the result file is selected, the stratification variable(s) must be selected along with a category variable (Figure 14). Then, based on the stratification variable(s), Plot\_ID and Plot\_# in the example of Figure 14, the values for a particular data source, such as a sample plot, may be selected to draw histograms (Figure 15). For the example in Appendix 3, the result is a window that displays density histograms for each species and time cycle in the input file, with menus to modify the size and colors of the histograms.

The command “Average histogram” is used to draw histograms that contain average values from different simulation result files. Figure 16 is an illustration of the form used to identify the input files. Following the selection of the input files, a form opens to select stratification and category variables (see Figure 14). This step is followed by a form to select the values of a particular data source, such as a sample plot, and the time cycles to display (see Figure 15). This functionality is used to display average values of different simulation scenarios performed on the same data source, such as a sample plot. Error bars based on standard deviations can be displayed.

### 3.6- Visual Add-ons menu

The menu “Visual Add-ons” may contain tools to visualize simulation results using virtual applications. The Stand Visualization System (SVS), developed by the USDA Forest Service, is currently the only virtual application that was implemented (note: SVS is currently non-functional).

**Selection of variables**

**Stratification Variables**

Available	Maximum 3	Selected
Plot_ID	> Remove	
Plot_#		

**Category Variables**

Available	Maximum 1	Selected
Species	> Remove	

Cancel OK

**Figure 14:** Input window to select the stratification and category variables to produce a distribution histogram.

**Select source of results**

**Stratification Variable(s)**

Plot\_ID: Edouard\_CO

Plot\_#: 65


**Time cycle**

- ☒ 0
- ☒ 5
- ☒ 10
- ☒ 15

All

Cancel OK

**Figure 15:** Following the identification of stratification and category variables, this form allows the selection of a specific source of results, such as a sample plot, at different time cycles.



**Figure 16:** Selection of input files to display average values on histograms.

### 3.7- QGIS menu

#### 3.7.1- Installing and running Quantum GIS

The QGIS menu manages or launches Quantum GIS, which is an application associated with AMSIMOD to visualize simulation results on digital maps at both site and landscape levels. The command “Setup” is used to identify the location of the folder that contains the executable file of Quantum GIS (Usually on C:\Program Files\ QGIS\*1\bin) and the location (folder) and QGIS file of the digital map that will be used to display results in the current AMSIMOD session (Figure 17). The command “Start” launches the execution of Quantum GIS using the digital map provided as input. The two parameters in the form illustrated in Figure 17 need to be provided only once in a workspace, as AMSIMOD records this information. Thus, it is possible to proceed directly to the command “Start” during a simulation session, unless a new digital map is loaded.

It is recommended to install the version 2.18.20 of Quantum GIS to ensure compatibility with the plugins associated with AMSIMOD. This version of Quantum GIS is available on the AMSIMOD web site: QGIS-OSGeo4W-2.18.20-1-Setup-x86.exe for the 32 bit version or QGIS-OSGeo4W-2.18.20-1-Setup-x86\_64.exe for the 64 bit version. When Quantum GIS is launched, it is recommended to select “Automatically enable on the fly reprojection if layers have different CRS” in the Options | CRS tab of the Settings menu. This option ensures that layers in a project will use the same coordinate reference system.

However, the launching of Quantum GIS from AMSIMOD can take considerable time. This long delay can be avoided by keeping Quantum GIS active after the initial launching. New simulation results can be displayed simply by loading a new map or re-loading the existing map in the “New” and “Open” sub-menus in the project menu.


---

<sup>1</sup>The asterisk indicates that the name of the folder beginning with QGIS can be followed by an identifier of the version of QGIS, such as Valmeira or Essen

### 3.7.2- Plugins

Two plugins were developed in Quantum GIS to facilitate the visualization of simulation results over time: “Position plots” and “TimeViewer”. They can be executed from the Plugins menu of Quantum GIS, provided that the folders “Plots” and “TimeViewer” are both installed in the folder C:\Users\{username}\.qgis2\python\plugins. The plugin “Position plots” is used to position and display sample plots on a digital map. When called, this plugin opens a form to enter a text file containing the labels that identify the sample plots to position (e.g., Edouard\_CO 65 in the example of Table 3), the type of spatial data used for each sample plot (1)<sup>2</sup> and position file names that contain information and spatial data for each sample plot. Table 3 is an example of the information to provide. Figure 18 is an illustration of the form that requests the name of a file (e.g., QGIS\_Output.txt) containing the information included in Table 3.

Every plot position file must include the identification and coordinates for each sample plot that will be positioned on a digital map (see Appendix 4). They can be created using the application “Create\_Plot\_Position\_Files.exe” (Appendix 5).




**Figure 17:** Form that opens when the command “Setup” is selected in the QGIS menu to enter the location of the executable file of Quantum GIS and the location and name of a digital map.

---

<sup>2</sup>Three types of spatial data for individual sample plots can be provided to “Position Plots” and “TimeViewer”. However, for the current version of AMSIMOD, the type of spatial data is limited to the positions of sample plots. It will be possible to provide other types of spatial data, such as individual-tree positions, in future releases of AMSIMOD.

**Table 3:** Example of the content of an input file provided to the plugin “Position plots” that contains the labels for the identification of sample plots (e.g., Edouard\_CO 65), type of coordinates used (e.g., 1) and plot position file names for sample plots to position on a digital map.

Edouard_CO 65 1	Edouard_65_code1.txt
Edouard_VI_O 67 1	Edouard_67_code1.txt
Edouard_O_CO 76 1	Edouard_76_code1.txt
Edouard_CO 77 1	Edouard_77_code1.txt
Edouard_CO 91 1	Edouard_91_code1.txt
Edouard_VI_O 122 1	Edouard_122_code1.txt
Edouard_VI_O 123 1	Edouard_123_code1.txt
Edouard_CO 129 1	Edouard_129_code1.txt
Edouard_CO 130 1	Edouard_130_code1.txt
Edouard_CO 131 1	Edouard_131_code1.txt
Edouard_O_CO 133 1	Edouard_133_code1.txt



**Figure 18:** Form that requests the name of a file, such as QGIS\_Output.txt, containing the names of the files that include the information and names of plot position files, such as those in Table 3.


The “TimeViewer” plugin is used to dynamically display simulation results using pie charts or circular charts (Figure 19). First, the “Position and result information” button must be pressed to select the file that contains the type of information indicated in Table 3 and the file that contains results to display on pie or circular charts. Normally, the file containing position information for each sample plot is the same file required by the plugin “Position plots”.

If the result file submitted to TimeViewer includes several results for each year and combination of stratification variables, pie charts will be drawn on the digital map. Following the selection of result and position files, a form opens to select a category variable, the result variable to display and the maximum number of sectors allowed on the pie charts (Figure 20). After clicking on the “Ok” button, the pie charts are drawn on the map and a legend is displayed (see example in


Appendix 6). The data of the variable to be displayed on each pie chart (selected in the form illustrated in Figure 20) are converted into percentages relative to the category variable for each year of the simulations. Table 2 is an example of a result file to draw pie charts for the category variable Species& for each combination of stratification variables (Plot\_ID\$ & Plot\_num\$). For each year and combination of Plot\_ID\$ and Plot\_num\$, the basal area values of the species (represented by Species\$) are summed to compute species-specific percentages.

If the result file submitted to TimeViewer includes a single result for each year and combination of stratification variables, circular charts will be drawn on the map. Table 4 is an example of the format of a result file to draw circular charts

The buttons associated with the controls in TimeViewer enable end users to control the dynamic visualization of results over time (Figure 19). The first two buttons of the controls are used to initiate or stop the dynamic visualization if the loop delay is 1 sec or greater. On the other hand, if the loop delay is 0 sec, it is possible to visualize manually the changes over time using the control buttons from the third to the sixth position. The combo menus “Step size”, “Year” and “Diameter” control the rate of the dynamic changes on the charts, the year to display and the diameter of the charts.



**Figure 19:** Illustration of the TimeViewer window that becomes visible in Quantum GIS when it is activated in the Plugins menu.



**Figure 20:** Illustration of the input window in TimeViewer to set the number of categories on pie charts and select a category variable and a quantitative variable to display on pie charts.

**Table 4:** Example of the format of a result file to display circular charts.


Year	Type_For\$	PlotNum\$	Biomass	Volume	Stem_Tape
0	Edouard_CO	65	100	50	0
1	Edouard_CO	65	100.9	50.9	0.1
2	Edouard_CO	65	102.6	52.6	0.2
3	Edouard_CO	65	105.2	55.2	0.29
4	Edouard_CO	65	108.7	58.7	0.38
0	Edouard_VI_O	67	100	50	0
1	Edouard_VI_O	67	100.9	50.9	0.1
2	Edouard_VI_O	67	102.6	52.6	0.2
3	Edouard_VI_O	67	105.2	55.2	0.29
4	Edouard_VI_O	67	108.7	58.7	0.38
0	Edouard_CO	77	100	50	0
1	Edouard_CO	77	100.9	50.9	0.1
2	Edouard_CO	77	102.6	52.6	0.2
3	Edouard_CO	77	105.2	55.2	0.29
4	Edouard_CO	77	108.7	58.7	0.38

### 3.8- Extensions menu

The menu “Extensions” is used to implement special applications or tools in AMSIMOD, such as numerical analytical applications to analyse simulation results or create intervention files.



These applications or tools normally consist of executable files (with the extension “.exe”) that can be developed in any programming language. It is possible to add or delete extensions (Figure 21). The submenu “Run” is used to execute one of the applications in the “Extensions” menu.




**Figure 21:** Examples of available applications in the menu “Extensions”.

### 3.9- Windows menu

This menu contains the list of all the windows created during an AMSIMOD session. This list is updated automatically when windows are created or deleted. A window that is selected in this menu becomes active.

**Appendix 1:** Example of the information provided to run a model within a project. There is one input file and 5 output files.



The image shows a 'Simulation Setup' dialog box with a blue title bar and standard window controls. The workspace is set to 'C:\Projects\_Folder\Projet\_Zelig\Exec\_Debug'. The simulation name is 'Succession'. The model selected is 'ZELIG\_CFS\_Model\_v37.exe'. The initialization file is 'Input\_LaMauricie\_Controls\_Version3.csv'. The intervention file is empty. The output files are 'Treedbh\_output', 'BasalArea\_Output', 'Density\_Output', 'PlotsInfo\_Output', and 'QGIS\_Output'. There are buttons for 'Select...', 'Comments', 'Delete', 'Update', and 'Cancel'.

Simulation Setup

Workspace : C:\Projects\_Folder\Projet\_Zelig\Exec\_Debug

Simulation name :  
Succession

Select a model (\*.exe, \*.bat):  
ZELIG\_CFS\_Model\_v37.exe Select...

Initialization file(s) (\*.txt, \*.csv):  
Input\_LaMauricie\_Controls\_Version3.csv Select...

Intervention file(s) (\*.txt):  
Select...

Output file(s):  
Treedbh\_output  
BasalArea\_Output  
Density\_Output  
PlotsInfo\_Output  
QGIS\_Output

Comments  
Delete

Update Cancel

**Appendix 2:** Example of C/C++ code to read input and output file names that are included in a project simulation.

In the example of Appendix 1, there is one initialization (input) file that must be opened to read the initialization data for a model and five output files that must be created. For the input file, the following code can be used in a model:

```
/* Read the name of the input file and open it to read the initialisation data of the
simulation. */
    gets(InpfileNameDriver);
    if ((InpFileDriver = fopen(InpfileNameDriver, modeinp)) == NULL)
    {
        /* Print error message, as the file did not open correctly. */
        /* If there is an error, gets out of the function and terminate the program. */

        printf("\n Problem to open the file %s \n", InpfileNameDriver); printf("\n <Press
return>");
        gets(InpfileName); goto endpgr;
    }
```

AMSIMOD automatically reads the character variable “InpfileNameDriver” using the function gets(), which is the name of an input file provided in an AMSIMOD project. An example of an input file is “Input\_LaMauricie\_Controls\_Version3.csv”. The next line contains the instructions to open the file “Input\_LaMauricie\_Controls\_Version3.csv” and assign it to InpFileDriver. This line of code also verifies if the file exists within the workspace. In case of a problem, an error message is displayed and the execution of the model is stopped. The content of the input file is subsequently assigned to specific variables in the model using C/C++ functions such as “fscanf()”. The same instructions to read input file names and open the files must be repeated for each input file provided to AMSIMOD in the definition of simulations in a project.

In the example of Appendix 1, there are five names of output files provided to AMSIMOD. The names of the output files are read and opened using the C/C++ functions “gets()” and “fopen()”. For instance:

```
gets(OutputExceldbh_Dr);
OutExceldbh = fopen(OutputExceldbh_Dr, 'w');
```

The function “gets()” reads the name “Treedbh\_output” (adds “.txt” if not there) and the function “fopen()” opens the file “Treedbh\_output.txt”. If this file does not exist, it is created. However, if the file already exists, data in the file is deleted. Then, the function “fprintf()” is used to write simulation results in the file. For instance, “fprintf(OutExceldbh, “\n %4d”, kyr);” writes the variable kyr in the output file “Treedbh\_output.txt”.

The following sequential calls must be included in the code of the model to create or open the output files listed in Appendix 1:

For BasalArea\_Output:

```
gets(OutputBasalArea_Dr);  
OutBasalArea = fopen(OutputBasalArea_Dr, 'w');
```

For Density\_Output:

```
gets(OutputDensity_Dr);  
OutDensity = fopen(OutputDensity_Dr, 'w');
```

For PlotsInfo\_Output:

```
gets(OutputPlotInfos_Dr);  
OutPlotInfos = fopen(OutputPlotInfos_Dr, 'w');
```

For QGIS\_Output data:

```
gets(OutputQGISfiles_Dr);  
OutQGISfiles = fopen(OutputQGISfiles_Dr, 'w');
```

**Appendix 3:** Example of the format of a data file to draw histograms.

An	Plot_ID\$	Plot_Num\$	Species&	Dhp_class@				
0	AmericanC	1	White_birch	0	25	37	87	0
0	AmericanC	1	Balsam_fir	0	12	0	12	0
0	AmericanC	1	Trembling_aspen	0	25	161	420	0
0	AmericanC	1	Black_spruce	0	87	111	185	12
0	AmericanC	1	Total	0	148	309	705	12
1	AmericanC	1	White_birch	0	25	37	87	0
1	AmericanC	1	Balsam_fir	0	12	0	12	0
1	AmericanC	1	Trembling_aspen	0	25	161	420	0
1	AmericanC	1	Black_spruce	0	87	111	185	12
1	AmericanC	1	Total	0	148	309	705	12
2	AmericanC	1	White_birch	0	25	37	87	0
2	AmericanC	1	Balsam_fir	0	12	0	0	0
2	AmericanC	1	Trembling_aspen	0	12	136	346	0
2	AmericanC	1	Black_spruce	0	74	111	185	12
2	AmericanC	1	Total	0	124	284	618	12
3	AmericanC	1	White_birch	0	25	37	87	0
3	AmericanC	1	Balsam_fir	0	12	0	0	0
3	AmericanC	1	Trembling_aspen	0	0	111	321	0
3	AmericanC	1	Black_spruce	0	62	111	185	12
3	AmericanC	1	Total	0	99	260	593	12

**Appendix 4:** Examples of two plot position files, generated by the application “Create\_Plot\_Position\_Files.exe” (Appendix 5), that contain information and spatial data for individual sample plots.

For rectangular plots:

-----  
Line 1: Strat2, Strat1, plot shape, plot size, geographic coordinate system  
Line 2: Edouard\_CO 65 rect 404.7 WGS84  
Line 3: Geographic coordinates.

Line 4:	1	-72.92327434	46.73590704
Line 5:	2	-72.92301276	46.73588651
Line 6:	3	-72.92301971	46.73570557
Line 7:	4	-72.92328289	46.73571035

-----

Line 1: Information on file content.  
Line 2: Information on plot identification (e.g., Edouard\_CO & 65), plot shape (rect for rectangular), plot area (e.g., 404.7 m<sup>2</sup>) and type of geographic coordinate system (also known as Coordinate Reference system in Quantum GIS).  
Line 3: Comment line to inform on geographic coordinates between lines 4 and 7.  
Lines 4 to 7: Geographic coordinates for the 4 corners of the rectangular sample plot.


For circular plots:

-----  
Line 1: Strat2, Strat1, plot shape, plot size, geographic coordinate system  
Line 2: Edouard\_CO 65 circ 404.7 NAD83/UTM\_zone\_15N  
Line 3: Geographic coordinates  
Line 4: 1        -72.92518632 46.73941847  
-----

Line 1: Information on file content.  
Line 2: Information on plot identification (e.g., Edouard\_CO 65), plot shape (circ for circular), plot area (404.7 m<sup>2</sup>) and type of geographic coordinate system (also known as Coordinate Reference system in Quantum GIS).  
Line 3: Information on geographic coordinates.  
Line 4: Geographic coordinates of the plot centre.

## Appendix 5: Introduction to the application “Create\_Plot\_Position\_Files.exe”.

The application “Create\_Plot\_Position\_Files.exe” was developed to facilitate and automate the creation of position files for individual sample plots, such as those illustrated in Appendix 4, to locate sample plots on digital maps. When the application is launched, the input form (see figure below) requests the name of a text file (.txt) that will contain the names of the position files created for each sample plot to be positioned on a digital map and two Excel files: (1) A file that contains, for each sample plot in a project, the identification code (e.g., Observation\_Area and PlotNum) and plot area and shape and (2) a file that contains, for each sample plot, the identification code, the coordinate system, latitude, longitude and altitude. Plot shape (PlotShape) can take two values: “rect” for rectangular plots and “circ” for circular plots.



Example of an Excel file that includes plot area and shape. In this example, the identification code includes two components: Observation\_area and PlotNum. A maximum of three identification variables are allowed.

Observation_area	PlotNum	PlotArea	PlotShape
SFPP	1	4046.9	rect
SFPP	2	4046.9	rect
SFPP	3	4046.9	rect
SFPP	4	4046.9	rect
SFPP	5	4046.9	rect

Example of an Excel file that includes the type of coordinate system, latitude, longitude and altitude.

Aire_observation	PlotNum	Coordinate_System	Latitude	Longitude	Altitude
SFPP	1	NAD83	49.1677770	-83.1361590	288
SFPP	10	NAD83	49.1679850	-83.1358640	288
SFPP	101	NAD83	49.3213430	-82.6096700	259
SFPP	104	NAD83	49.3198570	-82.6059090	254
SFPP	106	NAD83	49.3177930	-82.6018370	250
SFPP	107	NAD83	49.2907490	-82.5492670	240
SFPP	109	NAD83	49.2867820	-82.5484980	240

The coordinate system depends on the system used with the digital map. In this example, NAD83 is one of the systems used in North America. WGS84 is another coordinate system used in North America. If the option “Automatically enable on the fly reprojection if layers have different CRS in the Options | CRS tab of the Settings menu” is selected, as suggested above, Quantum GIS will adjust automatically to the specific coordinate reference system.

Using the information and data from both files, the application **Create\_Plot\_Position\_Files.exe** creates for each sample plot a file containing coordinate data, along with the appropriate information for either rectangular or circular sample plots. For each sample plot, the name of the position file is created automatically using plot identification information. For instance, for the plot in the table above with SFPP and 1 as Observation\_area and PlotNum, respectively, the file that is created will be “Coord\_SFPP\_1.txt” and its name will be recorded in the file that will contain the names of the position files (first element provided in the input form). All the plot position files created are recorded in a directory with a name beginning with “Files\_Coordinates...” followed by the date and time.



**Appendix 6:** Example of pie charts produced by the TimeViewer plugin on a digital map in Quantum GIS.

